

Link: <https://help.gpsinsight.com/docs/about-integration/using-customer-sites/> Last Updated: August 25th, 2016

Customer sites provides an API functionality that allows you to embed the HTML for a map with specific vehicle groups and/or landmarks on your own web server for visibility outside of the portal. Additionally, a KML flat file is provided via link for external **integrations** (e.g., ArcGIS). This feature allows your customers to view limited information about your vehicle locations without requiring the viewers to log in.



**Note.** In order to use Customer Sites, you must have the Customer Sites item enabled in the **Menu Access List** (Custom category).

### EXAMPLE


Company XYZ wants to post vehicle locations for their delivery vehicles on their public website so their customers can see when a delivery truck is in their zone.

### ► To create and share a customer site:

1. From the portal, click the **More** menu, click **Customer Sites**, and click **Open**.


The Manager Customer Sites page opens in a new browser tab.

1. In the Customer Site List grid, click **Customer Site** next to Create New.
2. In the New Customer Site window, enter the name of the site, and click **Create Site**.




The list of vehicles that belong to this customer site appears (no vehicles have yet been added).

1. From the right pane, **CTRL + click** to select the vehicle group(s) you want to add, and click **Add**.
2. Click **Save Changes**.



Link: <https://help.gpsinsight.com/docs/about-integration/using-customer-sites/> Last Updated: August 25th, 2016

---

1. In the Customer Site List grid, click the **Share** icon  next to the site.
2. In the Shared Link / HTML grid, copy the shared link OR copy and paste the HTML code in the box to your server to embed the map into your website.

▶ **To create and share a customer site for external integrations:**

1. Follow steps #1-6 provided under **To create and share a customer site.**
2. Click on the link in the box next to **KML:**.

A flat file containing the KML downloads for you to use in an external integration.

Link: <https://help.gpsinsight.com/docs/about-integration/using-customer-sites/> Last Updated: August 25th, 2016

## Shared Link / HTML



Shared Link:  
Email this link or use it in an iframe on your website.

<https://portal.gpsinsight.com/d/publicmap.php?key=gpsi56ba6e4434f5c>

HTML for site:  
Copy the code in this box to your server to view this same map on your website.  
*(For an older version, click here.)*

```
<!doctype html>  
<div data-trail-minutes="60" data-list-closed="false" data-trails="false" data-url-base="https://portal.gpsinsight.com" data-key="gpsi56ba6e4434f5c" style="width:800px;height:600px;" id="cust-site-map-canvas" data-google-api-key=""></div>  

```

KML:  
For external integrations.

<https://api.gpsinsight.com/v2/vehiclegroup/locationpublic.xml?kml=1&key=gpsi56ba6e4434f5c>

